# PDF-4+/Web 2023

PDF-4+/Web 2023 is licensed for use on a PC that has the PDF-4+/Web hardware dongle attached. The software may be installed on any number of computers; however, the licensed software can only be operated on the computer with the dongle attached. For concurrent access to the PDF-4+/Web database, additional licensed dongles must be purchased. Each dongle must be registered to enable a connection to the ICDD database server.

The PDF-4+/Web 2023 database contains integrated data mining software and ICDD's search-indexing software, Sleve+ (sold separately). In order for Sleve+ to be activated, a license for Sleve+ must be purchased from ICDD or your vendor. The full license period is for one year following the date of registration.

### **OEM and Vendor Software**

Please contact your software vendor to determine its compatibility with PDF-4+/Web 2023. Several OEM and vendor software packages support PDF-4+/Web 2023. In addition, some software vendors provide the ability to save their compiled index files to the dongle's 2GB of flash memory facilitating portability between computers.

Caution: A fee of \$500 USD will be charged to replace lost dongles. In order to receive a replacement dongle, you need to report the lost dongle's serial number to <a href="mailto:sales@icdd.com">sales@icdd.com</a>. ICDD will "turn-off" the lost dongle and ship a replacement dongle upon verification of your license.

# Licensing

Please carefully review the PDF-4+/Web 2023 license.

Windows 7 users: Click Start > All Programs > ICDD PDF-4+ Web 2023 > Read License.txt.

Windows® 8/8.1 users: Press the Windows® logo key for the "Start" screen, then click the tile labeled Lic-PDF-4+ Web 2023.

Windows® 10/11 users: Click Start > All apps > ICDD PDF-4+ Web 2023 > Read License.txt.

#### Installation

Your computer must satisfy the System Requirements in this document before continuing.

- 1. Get the latest installation file, PDF-4+ Web 2023.exe.
  - New user: The latest installation is on your USB dongle.

Renewing customer: Download from <a href="http://webpdf4.icdd.com/2023/downloads/">http://webpdf4.icdd.com/2023/downloads/</a>.

- 2. Close all running programs.
- 3. Run the installation with **Administrator** privileges and follow the on-screen instructions.
- 4. Activate your license for 2023.
  - a. Insert the PDF-4+/Web USB dongle.

Renewing customer will use his/her existing PDF-4+/Web USB dongle.

- b. Determine your operating system to register your PDF-4+/Web product directly at <a href="https://webpdf4.icdd.com/2023/registration/login.htm">https://webpdf4.icdd.com/2023/registration/login.htm</a>.
  - Windows 7 users: Click Start > All Programs > ICDD PDF-4+/Web 2023 > "Register ICDD Product"
  - Windows®8/8.1 users: Press the Windows® logo key for the "Start" screen, and then click the tile labeled "Register-PDF-4+ Web 2023".
  - Windows® 10/11 users: Click Start > All apps > ICDD PDF-4+ Web 2023 > Register ICDD Product.
- c. You will receive an email confirmation once the product is successfully registered.

# **Running the Software**

TCP/IP ports 3331 and 22220 must be open—see FAQ #2 and #3.

- 1. Insert the PDF-4+/Web USB dongle.
- 2. Launch the PDF-4+/Web 2023 using any account with **User** privileges.
  - Use the Desktop shortcut "PDF-4+ Web 2023" or Windows® 10 users: Click Start > All apps > ICDD PDF-4+ Web 2023 > "ICDD PDF-4+ Web 2023".

## **Stopping the Software**

- 1. Exit the PDF-4+/Web 2023 software.
- 2. Close the ICDD Communicator.
  - a. When closing the PDF-4+/Web software, you will be asked to close the ICDD Communicator. Select **Yes**.

or

- b. Close the ICDD Communicator by right-clicking on the ICDD Communicator icon in the System Tray (lower right screen) and selecting "Exit".
- 3. Eject the USB dongle by right-clicking on the turquoise CodeMeter icon in the System Tray and selecting "Eject all CmSticks".
- 4. Remove the PDF-4+/Web USB dongle.

#### **System Requirements**

#### Hardware:

Intel® Core™ 2 Duo processor or better 4 GB of system memory NTFS file system Fully-powered USB port 500 MB free hard drive space

## **Supported Operating Systems:**

Windows ® 7 SP1 Windows® 8/8.1 Windows® 10/11

# **Operating System Account Permissions:**

**Installation** requires **Administrator** privileges. **Running ICDD software** requires **User** privileges.

#### **Internet Access:**

Bandwidth: Minimum = 10 Mbps Preferred = 50 Mbps or faster

TCP/IP Ports: 3331 and 22220

TCP/IP ports require outbound access through all firewalls.

#### **RETURN POLICY**

Products may be returned within 30 days from the invoice date for a full refund or credit (excluding shipping/handling). Please visit <a href="http://www.icdd.com/ordering/">http://www.icdd.com/ordering/</a> for further information. Registered products do not qualify.

#### **HELP DOCUMENTATION & TUTORIALS**

Explore the capabilities of PDF-4+/Web 2023 with our extensive Help documentation, online tutorials and videos. The Help files include a Table of Contents and fundamental information on how to use the database. The online tutorials are designed to demonstrate the features, applications, hints and shortcuts for your PDF-4+ product. Please visit <a href="http://www.icdd.com/product-tutorials/">http://www.icdd.com/product-tutorials/</a>

## **SUPPORT**

www.icdd.com/support

Phone: 610.325.9814 • Toll-free in U.S.A. & Canada: 866.378.9331

Fax: 610.325.9823

Technical Support: support@icdd.com

Registration Support: registration@icdd.com

PDF-4+/Web 2023 contains integrated data mining software and ICDD's search-indexing software, Sleve+. A license for Sleve+ must be purchased from ICDD or your vendor in order for Sleve+ to be activated for the full license period.

International Centre for Diffraction Data
12 Campus Boulevard
Newtown Square, PA 19073-3273 USA
info@icdd.com
www.icdd.com • www.dxcicdd.com



ICDD, the ICDD logo and PDF are registered in the U.S. Patent and Trademark Office. Sleve+ is a trademark of JCPDS—International Centre for Diffraction Data.

©2023 ICDD 07/23